

User Manual 4.14 Dispersions

De Wiki

Aller à : [navigation](#), [rechercher](#)
[User Manual 4.14 Dispersions](#)

Introduction

Scope

This section describes how dispersions are defined and used in the PATRIUS library. Dispersions are not to be mixed up with random generation (not detailed in this page). Dispersions always rely on a random generator.

Javadoc

The dispersions objects are available in the package `fr.cnes.sirius.patrius.math.random`. This package also handles random generation.

Library

Patrius [Package fr.cnes.sirius.patrius.math.random](#)

Patrius [Package fr.cnes.sirius.patrius.math.random](#)

Javadoc

Links

None as of now.

Useful Documents

None as of now.

Package Overview

Features Description

Random number generation

Distributed random number generation is based on using implementations of interface `fr.cnes.sirius.patrius.math.random.NormalizedRandomGenerator`. Each implementation of this interface provides a specific dispersion scheme. For instance, the following code will generate random numbers with Gaussian distribution of mean 0 and unit standard deviation:

```
final RandomGenerator g = new JDKRandomGenerator();  
final NormalizedRandomGenerator generator = new GaussianRandomGenerator(g);  
final double value = generator.nextNormalizedDouble();
```

As shown in the above example, building a dispersion object requires a random generator implementing `fr.cnes.sirius.patrius.math.random.RandomGenerator` interface.

Random vector generation

Correlated random vector generation is based on using implementations of interface `fr.cnes.sirius.patrius.math.random.RandomVectorGenerator`. Each implementation of this interface provides a specific dispersion scheme. For instance, the following code will generate uniformly correlated random vectors according to provided covariance matrix:

```
final RandomGenerator g = new JDKRandomGenerator();
final RandomVectorGenerator generator = new
UniformlyCorrelatedRandomVectorGenerator(mean, covariance, 0, g);
final double[] value = generator.nextVector();
```

As shown in the above example, building a dispersion object requires a random generator implementing `fr.cnes.sirius.patrius.math.random.RandomGenerator` interface.

Correlated random vector generator

The user provides a covariance matrix and a random generator.

When using Gaussian correlated random vector generator:

- The covariance matrix root is extracted using a Cholesky decomposition. The number of columns of the root matrix corresponds to the rank of the provided covariance matrix.
- An uncorrelated vector of size the rank of the covariance matrix is generated using the provided random generator
- The final correlated vector is obtained by multiplying the covariance root matrix by this generated vector.

When using uniformly correlated random vector generator, the process is more complex:

- The covariance matrix is converted into a correlation matrix. Standard deviation vector is extracted from the process. Obtained correlation matrix must be positive semi-definite (all eigenvalues must be non negative).
- Spearman correction is applied to the correlation matrix. If corrected correlation matrix is not positive semi-definite, correction is not applied.



- The correlation matrix root is extracted using a Cholesky decomposition. The number of columns of the root matrix corresponds to the rank of the correlation matrix.
- A uncorrelated vector of size the rank of the covariance matrix is generated using the provided random generator
- The product of correlation matrix root L and uncorrelated vector T is then transformed to get a uniform law:



- The final correlated vector is obtained by linearly multiplying z by the standard deviation vector.

Getting Started

[Modèle:SpecialInclusion prefix=\\$theme section="GettingStarted"/](#)

Contents

Interfaces

The library defines the following interfaces related to dispersions:

Interface	Summary	Javadoc
NormalizedRandomGenerator	Interface for normalized random generators	...
RandomVectorGenerator	Interface for random vector generators	...

Note: interface for random number generators is
`fr.cnes.sirius.patrius.math.random.RandomGenerator`.

Classes

The library defines the following classes related to dispersions:

Class	Summary	Javadoc
GaussianRandomGenerator	Generator following Gaussian distribution	...
UniformRandomGenerator	Generator following uniform distribution	...
UncorrelatedRandomVectorGenerator	Generator for Gaussian uncorrelated vectors	...
CorrelatedRandomVectorGenerator	Generator for Gaussian correlated vectors	...
UniformlyCorrelatedRandomVectorGenerator	Generator for uniformly correlated vectors	...
UnitSphereRandomVectorGenerator	Generator for vectors isotropically located on a sphere	...

Récupérée de « http://patrius.cnes.fr/index.php?title=User_Manual_4.14_Dispersions&oldid=3754 »
[Catégorie](#) :

- [User Manual 4.14 Mathematics](#)

Menu de navigation

Outils personnels

- [3.133.140.88](#)
- [Discussion avec cette adresse IP](#)
- [Créer un compte](#)
- [Se connecter](#)

Espaces de noms

- [Page](#)
- [Discussion](#)

Variantes

Affichages

- [Lire](#)
- [Voir le texte source](#)
- [Historique](#)
- [Exporter en PDF](#)

Plus

Rechercher

PATRIUS

- [Welcome](#)

Evolutions

- [Main differences between V4.15 and V4.14](#)
- [Main differences between V4.14 and V4.13](#)
- [Main differences between V4.13 and V4.12](#)
- [Main differences between V4.12 and V4.11](#)
- [Main differences between V4.11 and V4.10](#)
- [Main differences between V4.10 and V4.9](#)
- [Main differences between V4.9 and V4.8](#)
- [Main differences between V4.8 and V4.7](#)
- [Main differences between V4.7 and V4.6.1](#)
- [Main differences between V4.6.1 and V4.5.1](#)
- [Main differences between V4.5.1 and V4.4](#)
- [Main differences between V4.4 and V4.3](#)
- [Main differences between V4.3 and V4.2](#)
- [Main differences between V4.2 and V4.1.1](#)
- [Main differences between V4.1.1 and V4.1](#)
- [Main differences between V4.1 and V4.0](#)
- [Main differences between V4.0 and V3.4.1](#)

User Manual

- [User Manual 4.15](#)

- [User Manual 4.14](#)
- [User Manual 4.13](#)
- [User Manual 4.12](#)
- [User Manual 4.11](#)
- [User Manual 4.10](#)
- [User Manual 4.9](#)
- [User Manual 4.8](#)
- [User Manual 4.7](#)
- [User Manual 4.6.1](#)
- [User Manual 4.5.1](#)
- [User Manual 4.4](#)
- [User Manual 4.3](#)
- [User Manual 4.2](#)
- [User Manual 4.1](#)
- [User Manual 4.0](#)
- [User Manual 3.4.1](#)
- [User Manual 3.3](#)

Tutorials

- [Tutorials 4.15](#)
- [Tutorials 4.14](#)
- [Tutorials 4.13.5](#)
- [Tutorials 4.12.1](#)
- [Tutorials 4.8.1](#)
- [Tutorials 4.5.1](#)
- [Tutorials 4.4](#)
- [Tutorials 4.1](#)
- [Tutorials 4.0](#)

Links

- [CNES freeware server](#)

Navigation

- [Accueil](#)
- [Modifications récentes](#)
- [Page au hasard](#)
- [Aide](#)

Outils

- [Pages liées](#)
- [Suivi des pages liées](#)
- [Pages spéciales](#)
- [Adresse de cette version](#)

- [Information sur la page](#)
- [Citer cette page](#)

- Dernière modification de cette page le 5 septembre 2024 à 14:56.

- [Politique de confidentialité](#)
- [À propos de Wiki](#)
- [Avertissements](#)

- 