

# User Manual 3.3 Attitude leg

De Wiki

Aller à : [navigation](#), [rechercher](#)

[User Manual 3.3 Attitude leg](#)

## Sommaire

- [1 Introduction](#)
  - [1.1 Scope](#)
  - [1.2 Javadoc](#)
  - [1.3 Links](#)
  - [1.4 Useful Documents](#)
  - [1.5 Package Overview](#)
- [2 Features Description](#)
  - [2.1 Generalities](#)
  - [2.2 Available attitude leg](#)
    - [2.2.1 Attitude legs sequence](#)
    - [2.2.2 TabulatedAttitude](#)
    - [2.2.3 RelativeTabulatedAttitudeLeg](#)
- [3 Getting Started](#)
  - [3.1 Building an attitude legs sequence](#)
  - [3.2 AttitudeLawLeg and AttitudeLegsSequence : Code sample](#)
- [4 Contents](#)
  - [4.1 Interfaces](#)
  - [4.2 Classes](#)

## Introduction

### Scope

The purpose of this chapter is to describe the current Patrius attitude legs.

An attitude leg is a time-bounded attitude law. Generalities on attitude laws can be found [here](#).

### Javadoc

Library	Javadoc
Orekit	<a href="#">Package org.orekit.attitudes</a>
Orekit addons	<a href="#">Package org.orekit.attitudes</a>

### Links

*Orekit Attitudes architecture description, [Orekit site](#).*

## Useful Documents

[Modèle:SpecialInclusion prefix=\\$theme sub\\_section="UsefulDocs"/](#)

## Package Overview

The attitude leg `AttitudeLeg` interface inherits the `AttitudeProvider` interface. Its place in the global Attitude design can be found [here](#).

## Features Description

### Generalities

Attitude legs inherit the interface `AttitudeLeg`. They are time-bounded attitude providers. In addition to `AttitudeProvider` services, they provide the method `getTimeInterval()` returning the leg timespan.

### Available attitude leg

#### Attitude legs sequence

An attitude legs sequence is a container for several attitude legs, contiguous for their time intervals, in such a way that the attitude legs sequence can be processed like a single attitude leg by the propagator.

The attitude legs sequence is the equivalent of the [Attitudes sequence](#), using attitude legs (`AttitudeLeg` instances) rather than attitude laws (`AttitudeLaw` instances). The switching from one attitude leg to another is based on the time interval of validity of the two legs.

An attitude legs sequence is associated to a `PVCoordinatesProvider` instance, which will **override any PVCoordinatesProvider** passed as parameter to the methods like `getAttitude()`. The reason for such a behaviour, which violates the contract of the `AttitudeProvider` interface, is that :

- an attitude legs sequence needs to **enforce coherence** between its inner attitude legs and its homing maneuvers.
- homing maneuvers are created and computed once by using a specific `PVCoordinatesProvider`, in order to preserve good performances.

Therefore, the attitude legs sequence can only compute attitudes with the `PVCoordinatesProvider` instance it was built with, and the inner attitude legs should be coherent with this provider (the attitude sequence does not check if it's the case!)

#### TabulatedAttitude

`TabulatedAttitude` is an implementation of `AttitudeLeg`. It represents a tabulated attitude leg.

In order to interpolate the attitude at a date, the user must specify a list of **ordered** attitudes, and can specify a number of points used by Hermite interpolation. If not specified, the number of points used by Hermite interpolation is set to a default number (currently 2).

```

final List<Attitude> attList = new ArrayList<Attitude>();
attList.add(attitude0);
attList.add(attitude1);
final int nbrInterpPoints = 2;
final TabulatedAttitude attLeg = new TabulatedAttitude(attList,
nbrInterpPoints);

```

It is possible to get the non-interpolated ordered attitudes :

```
final List<Attitude> attitudes = attLeg.getAttitudes();
```

Once the tabulated is defined, the computation can be performed on any orbital state using `getAttitude()` method:

```
Attitude attitude = attLeg.getAttitude(orbit, date,
FramesFactory.getEME2000());
```

## RelativeTabulatedAttitudeLeg

`RelativeTabulatedAttitudeLeg` is an implementation of `AttitudeLeg`. An instance of `RelativeTabulatedAttitudeLeg` can be created with a `List<Pair<Double, Rotation>>` or with a `List<Pair<Double, AngularCoordinates>>`. Each `Rotation` (or `AngularCoordinates`) is associated with a double representing its time ellapsed in seconds since the reference date. Here is an example of a creation of an instance of `RelativeTabulatedAttitudeLeg` :

```

// date and frame
AbsoluteDate refDate = new AbsoluteDate(2008, 1, 1,
TimeScalesFactory.getTAI());
Frame frame = FramesFactory.getGCRF();
double timeEllapsedSinceRefDate = 1.0;

// List of AR
List<Pair<Double, AngularCoordinates>> listAr = new ArrayList<Pair<Double,
AngularCoordinates>>();
final AngularCoordinates ar = new AngularCoordinates(
    new Rotation(false, 0.48, 0.64, 0.36, 0.48), Vector3D.PLUS_I,
Vector3D.PLUS_J);
listAr.add(new Pair<Double, AngularCoordinates>(timeEllapsedSinceRefDate,
ar));

// create RelativeTabulatedAttitudeLeg
final RelativeTabulatedAttitudeLeg relativeTabulatedAttitudeLeg =
    new RelativeTabulatedAttitudeLeg(refDate, frame, listAr);

```

# Getting Started

## Building an attitude legs sequence

The attitude legs sequence was designed as a simple container, it performs only a few coherence checks on its inner attitude laws. Here's how an attitude sequence is built.

- An attitude legs sequence is created empty, associated to a single PVCoordinatesProvider instance.
- The sequence is mutable, attitude laws can be added to it one by one.
- Each attitude law is identified by a code.
- The sequence has a validity time interval, which is the grouping of the validity time intervals of all contained laws.
- The time interval of a newly added law must be contiguous to the grouped time interval of the already added laws. Otherwise an OrekitException is thrown.
- As soon as the sequence contains at least one law, methods of the AttitudeLeg interface can be called on the attitude sequence. The attitude sequence forwards the request to the appropriate attitude leg (according to the asking date), but replaces the PVCoordinatesProvider attribute of the call with the inner PVCoordinatesProvider instance.

## AttitudeLawLeg and AttitudeLegsSequence : Code sample

```
final BodyCenterPointing earthCenterAttitudeLaw = new
BodyCenterPointing(itrf);
final AttitudeLeg law1 = new AttitudeLawLeg(earthCenterAttitudeLaw, date1,
date2);
final AttitudeLeg law2 = ... ;
final AttitudeLeg law3 = ... ;

PVCoordinatesProvider pvProvider = new CartesianOrbit(pvCoordinates, gcrf,
date1, mu);
final AttitudeLegsSequence sequence = new AttitudeLegsSequence(pvProvider);
// After each add the sequence has to be contiguous, so the order may be
important
sequence.add("L1", law1);
sequence.add("L2", law2);
sequence.add("L3", law3);

// Call to getAttitude on the sequence ignores otherPvProvider and uses
pvProvider internally instead
final Attitude sAttitude = sequence.getAttitude(otherPvProvider, date, itrf);
```

## Contents

## Interfaces

Interface	Summary	Javadoc
<b>AttitudeLeg</b>	This interface extends the AttitudeProvider interface and adds the time interval of validity notion to the attitude laws.	<a href="#">...</a>

## Classes

Class	Summary	Javadoc
<b>AttitudeLawLeg</b>	Object representing an attitude law for spacecraft attitude field purposes.	<a href="#">...</a>
<b>TabulatedAttitude</b>	Object representing a tabulated attitude leg : the attitude at a date is interpolated from a list of known ones.	<a href="#">...</a>
<b>AttitudeLegsSequence</b>	Object representing a sequence of contiguous attitude legs.	<a href="#">...</a>
<b>RelativeTabulatedAttitudeLeg</b>	This class implements a tabulated attitude leg with relative dates.	<a href="#">...</a>

Récupérée de « [http://patrius.cnes.fr/index.php?title=User\\_Manual\\_3.3\\_Attitude\\_leg&oldid=1295](http://patrius.cnes.fr/index.php?title=User_Manual_3.3_Attitude_leg&oldid=1295) »

Catégorie :

- [User Manual 3.3 Attitude](#)

## Menu de navigation

### Outils personnels

- [3.141.201.95](#)
- [Discussion avec cette adresse IP](#)
- [Créer un compte](#)
- [Se connecter](#)

### Espaces de noms

- [Page](#)
- [Discussion](#)

### Variantes

### Affichages

- [Lire](#)
- [Voir le texte source](#)
- [Historique](#)
- [Exporter en PDF](#)

## **Plus**

### **Rechercher**

<input type="text"/>	<input type="button" value="Rechercher"/>	<input type="button" value="Lire"/>
----------------------	---	-------------------------------------

## **PATRIUS**

- [Welcome](#)

## **Evolutions**

- [Main differences between V4.15 and V4.14](#)
- [Main differences between V4.14 and V4.13](#)
- [Main differences between V4.13 and V4.12](#)
- [Main differences between V4.12 and V4.11](#)
- [Main differences between V4.11 and V4.10](#)
- [Main differences between V4.10 and V4.9](#)
- [Main differences between V4.9 and V4.8](#)
- [Main differences between V4.8 and V4.7](#)
- [Main differences between V4.7 and V4.6.1](#)
- [Main differences between V4.6.1 and V4.5.1](#)
- [Main differences between V4.5.1 and V4.4](#)
- [Main differences between V4.4 and V4.3](#)
- [Main differences between V4.3 and V4.2](#)
- [Main differences between V4.2 and V4.1.1](#)
- [Main differences between V4.1.1 and V4.1](#)
- [Main differences between V4.1 and V4.0](#)
- [Main differences between V4.0 and V3.4.1](#)

## **User Manual**

- [User Manual 4.15](#)
- [User Manual 4.14](#)
- [User Manual 4.13](#)
- [User Manual 4.12](#)
- [User Manual 4.11](#)
- [User Manual 4.10](#)
- [User Manual 4.9](#)
- [User Manual 4.8](#)
- [User Manual 4.7](#)
- [User Manual 4.6.1](#)
- [User Manual 4.5.1](#)
- [User Manual 4.4](#)

- [User Manual 4.3](#)
- [User Manual 4.2](#)
- [User Manual 4.1](#)
- [User Manual 4.0](#)
- [User Manual 3.4.1](#)
- [User Manual 3.3](#)

## Tutorials

- [Tutorials 4.15](#)
- [Tutorials 4.14](#)
- [Tutorials 4.13.5](#)
- [Tutorials 4.12.1](#)
- [Tutorials 4.8.1](#)
- [Tutorials 4.5.1](#)
- [Tutorials 4.4](#)
- [Tutorials 4.1](#)
- [Tutorials 4.0](#)

## Links

- [CNES freeware server](#)

## Navigation

- [Accueil](#)
- [Modifications récentes](#)
- [Page au hasard](#)
- [Aide](#)

## Outils

- [Pages liées](#)
- [Suivi des pages liées](#)
- [Pages spéciales](#)
- [Adresse de cette version](#)
- [Information sur la page](#)
- [Citer cette page](#)

• Dernière modification de cette page le 28 février 2018 à 15:11.

- [Politique de confidentialité](#)
- [À propos de Wiki](#)
- [Avertissements](#)
-